

OVERVIEW

The Systech UniScan app must be installed on the iPhone using iTunes and the iPhone must be registered with Systech.

REQUIREMENTS

Installing the UniScan app requires an iPhone 4S or above, a mobile provision file, and a PC with iTunes installed. To obtain a copy of the mobile provision file, follow "Acquiring the eFingerprintProfile.mobileprovision file" below.

ACQUIRING THE EFINGERPRINTPROFILE.MOBILEPROVISION FILE

1. Connect the iPhone to the PC and open iTunes.
2. Click the iPhone button to view information pertaining to that iPhone.
3. Click on the serial number as shown in Figure 1 to reveal the UDID.
4. Send the UDID, as shown in Figure 2, to Candice.Cassella@SystechOne.com via email.
5. The request will be processed and the eFingerprintProfile.mobileprovision file will be sent back to the requester.
6. Upon receipt of the mobile provision file, follow instructions below to install the UniScan app.



FIGURE 1

[Click here](#)



FIGURE 2

[Send the UDID to Systech](#)

INSTALLING THE UNISCAN LICENSE AND APP VIA iTunes

1. Save the eFingerprintProfile.mobileprovision and App.ipa files on the desktop of the PC.
2. Connect the iPhone to the PC.
3. Using iTunes, select **Add File to Library...** as shown in Figure 3.
4. Navigate to the desktop, select the eFingerprintProfile.mobileprovision file and click **Open**.
5. Click the **iPhone** button to see the contents of the device as shown in Figure 4.
6. Using iTunes, select Add File to Library... as shown in Figure 3.
7. Navigate to the desktop, select the App.ipa file and click Open.
8. Navigate to the "Apps" tab, under the settings menu, and press the "Install" button next to the UniScan app name, as shown in Figure 5.
9. When the button changes to "Will Install", click the Sync button as shown in Figure 6
10. When the sync is completed, eject the iPhone.
11. Disconnect the iPhone from the PC.
12. Once installed, run the app and go to the Settings menu.
13. Enter the Systech provided values specific to your program. See the Configuration Settings section below for an example of the values that need to be entered.



FIGURE 3



FIGURE 4




FIGURE 5




FIGURE 6

CONFIGURATION SETTINGS

Table 1 shows the fields that need to be populated. Please refer to your UniScan welcome packet for the values to properly populate these fields for your program.

FIELD NAME	INPUT DATA	DEFAULT
Email:	<your email address>	Empty
Phone Number:	<your cell phone number>	Empty
Server URL:	<server url>	Empty
Server Username:	<server username>	Empty
Server Password:	<server password>	Empty
Barcode Type:	<barcode type>	Empty
Barcode Size Class:	<size class>	Empty
Sharpness:	<sharpness>	Empty
Laser Ablation:	<on for laser ablation>	Off
Flash On:	<on to enable Flash>	On

TABLE 1: CONFIGURATION SETTINGS